

Zabezpečení Proxmox VE

Reverzní proxy před pveproxy

Návod volně založen na <http://the-bleeding-edge.info/blog/?p=24>

[/etc/default/pveproxy](#)

```
ALLOW_FROM="127.0.0.1"  
DENY_FROM="all"  
POLICY="allow"
```

`/etc/init.d/pveproxy restart`

`apt install nginx-light`

[/etc/nginx/sites-available/proxmox](#)

```
## Momentálne koliduje s letsencryptem, tak to je zakazany nez to bude  
## mozny nakombinovat  
#server {  
#    listen 80;  
#    server_name _;  
#    return 302 https://$hostname$request_uri;  
#}  
  
server {  
    listen 443 ssl; #choose your port or just use 443  
    server_name _; #place your domain or ip here if needed  
  
    #root /usr/share/nginx/www;  
  
    ssl_certificate  
/etc/letsencrypt/live/pvel.spoje.net/fullchain.pem;  
    ssl_certificate_key  
/etc/letsencrypt/live/pvel.spoje.net/privkey.pem;  
  
    proxy_redirect off;  
  
    auth_basic "SPOJE.NET VPS";  
    auth_basic_user_file /etc/nginx/.htpasswd;  
  
    #proxy_ssl_verify off; #default  
  
    location ~ ^.+websocket$ {  
        proxy_pass https://127.0.0.1:8006;
```

```
        proxy_set_header Upgrade $http_upgrade;
        proxy_set_header Connection "upgrade";
    }

    location / {
        proxy_pass https://127.0.0.1:8006;
    }
}
```

```
username=virtual; echo "${username}:\`openssl passwd -apr1`" >>
/etc/nginx/.htpasswd
```

```
/etc/init.d/nginx restart
```

From:
<https://wiki.spoje.net/> - **SPOJE.NET**

Permanent link:
<https://wiki.spoje.net/doku.php/howto/vps/proxmox-ve/security?rev=1500398885>

Last update: **2017/07/18 19:28**

