

# Zabezpečení Proxmox VE

## Reverzní proxy před pveproxy

Návod volně založen na

- <http://the-bleeding-edge.info/blog/?p=24>
- <https://www.jamescoyle.net/how-to/1522-proxy-the-proxmox-web-gui-with-nginx-over-https-with-load-balancing>

`/etc/default/pveproxy`

```
ALLOW_FROM="127.0.0.1"  
DENY_FROM="all"  
POLICY="allow"
```

`/etc/init.d/pveproxy restart`

`apt install nginx-light`

`/etc/nginx/sites-available/proxmox`

```
## Momentálne koliduje s letsencryptem, tak to je zakazany nez to bude  
## mozny nakombinovat  
#server {  
#     listen 80;  
#     server_name _;  
#     return 302 https://$hostname$request_uri;  
#}  
  
server {  
    listen 443 ssl; #choose your port or just use 443  
    server_name _; #place your domain or ip here if needed  
  
    #root /usr/share/nginx/www;  
  
    ssl_certificate  
/etc/letsencrypt/live/pvel.spoje.net/fullchain.pem;  
    ssl_certificate_key  
/etc/letsencrypt/live/pvel.spoje.net/privkey.pem;  
  
    proxy_redirect off;  
  
    auth_basic "SPOJE.NET VPS";  
    auth_basic_user_file /etc/nginx/.htpasswd;  
  
    #proxy_ssl_verify off; #default
```

```
location ~ ^.+websocket$ {
    proxy_pass https://127.0.0.1:8006;
    proxy_set_header Upgrade $http_upgrade;
    proxy_set_header Connection "upgrade";
}

location / {
    proxy_pass https://127.0.0.1:8006;
}
}
```

```
username=virtual; echo "${username}:\`openssl passwd -apr1`" >>
/etc/nginx/.htpasswd
```

/etc/init.d/nginx restart

## LXC - Zakázat dmesg

</usr/share/lxc/config/common.seccomp>

```
...
syslog errno 1
```

From:  
<https://wiki.spoje.net/> - **SPOJE.NET**

Permanent link:  
<https://wiki.spoje.net/doku.php/howto/vps/proxmox-ve/security?rev=1506388829>

Last update: **2017/09/26 03:20**

