

Dell G5

- https://wiki.debian.org/NVIDIA%20Optimus#Using_nvidia-xrun
- <https://wiki.debian.org/Bumblebee#Installation>
- <https://wiki.archlinux.org/title/bumblebee>
- https://wiki.archlinux.org/title/NVIDIA_Optimus

/etc/default/grub

```
GRUB_CMDLINE_LINUX="nvidia-drm.modeset=1"
```

/etc/modules

```
nvidia
nvidia_drm
nvidia_modeset
nvidia_uvm
```

/etc/modprobe.d/nvidia.conf

```
install nvidia modprobe -i nvidia-current $CMDLINE_OPTS

install nvidia-modeset modprobe nvidia ; modprobe -i nvidia-current-modeset
$CMDLINE_OPTS

install nvidia-drm modprobe nvidia-modeset ; modprobe -i nvidia-current-drm
$CMDLINE_OPTS

install nvidia-uvm modprobe nvidia ; modprobe -i nvidia-current-uvm
$CMDLINE_OPTS

install nvidia-peermem modprobe nvidia ; modprobe -i nvidia-current-peermem
$CMDLINE_OPTS

# unloading needs the internal names (i.e. upstream's names, not our renamed
files)

remove nvidia modprobe -r -i nvidia-drm nvidia-modeset nvidia-peermem
nvidia-uvm nvidia

remove nvidia-modeset modprobe -r -i nvidia-drm nvidia-modeset

alias char-major-195* nvidia

# These aliases are defined in *all* nvidia modules.
# Duplicating them here sets higher precedence and ensures the selected
# module gets loaded instead of a random first match if more than one
# version is installed. See #798207.
```

```
alias pci:v000010DEd00000E00sv*sd*bc04sc80i00* nvidia
alias pci:v000010DEd00000AA3sv*sd*bc0Bsc40i00* nvidia
alias pci:v000010DEd*sv*sd*bc03sc02i00* nvidia
alias pci:v000010DEd*sv*sd*bc03sc00i00* nvidia

options nvidia-drm modeset=1
```

nvidia-xconfig -prime (mel by neco vygenerovatm kdyztak upravit) /etc/X11/xorg.conf

```
# nvidia-xconfig: X configuration file generated by nvidia-xconfig
# nvidia-xconfig: version 470.103.01
```

```
Section "ServerLayout"
    Identifier      "Layout0"
    Screen         0  "Screen0"
    Inactive        "InactiveDevice1"
    InputDevice     "Keyboard0" "CoreKeyboard"
    InputDevice     "Mouse0"  "CorePointer"
EndSection
```

```
Section "Files"
EndSection
```

```
Section "InputDevice"
    # generated from default
    Identifier      "Mouse0"
    Driver          "mouse"
    Option          "Protocol" "auto"
    Option          "Device"   "/dev/psaux"
    Option          "Emulate3Buttons" "no"
    Option          "ZAxisMapping" "4 5"
EndSection
```

```
Section "InputDevice"
    # generated from default
    Identifier      "Keyboard0"
    Driver          "kbd"
EndSection
```

```
Section "Monitor"
    Identifier      "Monitor0"
    VendorName     "Unknown"
    ModelName      "Unknown"
    Option          "DPMS"
EndSection
```

```
Section "Device"
    Identifier      "Device0"
    Driver          "nvidia"
    VendorName     "NVIDIA Corporation"
    BusID          "PCI:1:0:0"
```

```
EndSection

Section "Device"
    Identifier      "InactiveDevice1"
    Driver          "modesetting"
    VendorName     "Unknown"
EndSection

Section "Screen"
    Identifier      "Screen0"
    Device          "Device0"
    Monitor         "Monitor0"
    DefaultDepth    24
    Option          "AllowEmptyInitialConfiguration" "True"
    SubSection      "Display"
        Depth         24
    EndSubSection
EndSection
```

From:
<https://wiki.spoje.net/> - **SPOJE.NET**



Permanent link:
<https://wiki.spoje.net/doku.php/howto/desktop/dell>

Last update: **2023/05/02 17:00**